

# Merchandise Manager 5.0.0.1002 Gift Cards


Below are the steps to create and use gift cards in the Merchandise Manager system.

- 1) Determine the gift card format.
- 2) Add inventory items that allow selling a gift card.
- 3) Sell a new gift card.
- 4) Use the gift card as payment for merchandise.


Double Click the Merchandise Manager Back office Icon from the center of your desktop.



Select your company name and System Manager as the login user. Manager has special privileges. Enter a password if needed and click Log In.



- 1) Determine the gift card format.



Select Utility Menu from the Main Menu

Select CCardSetup from the Utilities Menu



Use the Gift Card Setup to determine how the gift card is stored.

A screenshot of the 'CCard Setup' window. It has a title bar with a close button. Below the title bar is a 'Swipe Card' field with a sequence of zeros and plus signs, and an 'Example' button. There are two radio buttons for 'Track 1' (selected) and 'Track 2'. Under 'Track 1 Information', there are three input fields for 'Account Number Field 1,2,3' (value 1), 'Expiration Field 1,2,3' (value 2), and 'Account Name Field 1,2,3' (value 3). To the right, 'Track 2 Information' includes fields for 'Account Number Scanning Position' (1), 'Account Number Length' (16), 'Expiration Date Starting Position' (18), 'Expiration Date Length' (4), 'Account Name Scanning Position' (0), and 'Account Name Length(0 if none)' (0). A 'Minimum Swipe Length' field is set to 32. 'Save' and 'Exit' buttons are present. Below this are sections for 'Gift Card Setup', 'Shopper Card Setup', and 'Salesperson Card Setup', each with a 'Swipe Card' field and associated configuration fields like 'Card Number Length' and 'Card Begins With'.

Place the cursor in the swipe card section and either scan or swipe a gift card. Sometimes the gift card has special characters when it is scanned/swiped and these need to be handled.


A close-up screenshot of the 'Gift Card Setup' section. The 'Swipe Card' field contains the scanned text ';7018243380001308=?'. The 'Card Number Length' field is set to 19, 'Card Begins With' is ;7018, and 'Gift Card No Starts at (1 - 9)' is 2. The 'Gift Card No Length' field is 16.

After scanning this card, we see special characters. The card number we want to use is 7018243380001308  
The Gift Card number starts at position 2.  
The Card Number Length is 19. (This is the scanned card length)  
The Card starts with ;7018  
The Gift Card No Length is 16.

If the scanned card is 7018243380001308 (No special characters) the setup will be:

A close-up screenshot of the 'Gift Card Setup' section. The 'Swipe Card' field contains the clean card number '7018243380001308'. The 'Card Number Length' field is set to 16, 'Card Begins With' is 7018, and 'Gift Card No Starts at (1 - 9)' is 1. The 'Gift Card No Length' field is 16.

Make sure a payment type is set up properly for Gift Cards.




Select Utility Menu from the Main Menu



Select Pay Types from the Utilities Menu

Make sure there is a Gift Card option that contains GCARD in the Ref1 field.



- 2) Add inventory items that allow selling a gift card.  
Inventory Items associated with Gift Cards all start with GCARD in the item number.

Create an item with GCARD in the item number field. Just Enter Gift Card in the Description. Make sure the Product Category is Gift Cards. Create a new Product Category if one does not exist. Enter zero in the Price.

The screenshot shows the 'Item Maintenance' window with the following fields and values:

- Item No: GCARD
- Description: Gift Card
- Product Category: Gift Cards
- On Hand: -3
- Price: 0.00
- Case Cost: 0.00
- Indiv. Cost: (empty)
- Average Cost: (empty)
- Unit of Measure: (empty)
- Additional Information: (empty)

To create a preset dollar amount gift card, enter GCARDXX where XX is the dollar amount of the card.

The screenshot shows the 'Item Maintenance' window with the following fields and values:

- Item No: GCARD50
- Description: Gift Card 50
- Product Category: Gift Cards
- On Hand: 0
- Price: 50.00
- Case Cost: 0.00
- Indiv. Cost: 0.00
- Average Cost: 0.00
- Unit of Measure: (empty)
- Additional Information: (empty)

Enter the value of the gift card in the price field.

NOTE: Speed Buttons can be set up to allow selling a Gift Card by pressing a button at the register. Just make sure the GCARD or GCARD50 is used as the item number on that button.

3) Sell a new gift card.

A) Scan an unused gift card at the register.

User: SYSTEM MAN Drawer: 1 Customer: Cash Sale Balance: \$0.00

Sales man View Sales Gift Cards Inventory Credit Cards Override Active Sale No

Item No	Description	Qty	Price	Disc %	UM	Amount
7018243380001308						

Save Delete Void Cancel

Misc Non-Taxable Misc Taxable Incense Cup of Ice Save Sale Retrieve Sa

If that gift card number has not already been used, the following will display.

Information

This gift card is not currently on file.

OK

Press OK

Sales man View Sales Gift Cards Inventory Credit Cards

Item No	Description	Qty	Price	Disc %	UM	Amount
GCARD	New Gift Card-7018243380001308	1	25.00			

Save Void

Items: 0

Discount \$0.00 Total \$0.00

Paid Char

7 8 9 4 5 6 1 2 3 0 00 . Canc... Clear Enter

Enter the dollar amount of the gift card.

Sales man View Sales Gift Cards Inventory Credit Cards Override

Item No. Description Save Delete  
 Qty Price Disc % Void Cancel

Item No	Description	Qty	Price	Disc	UM	Amount
GCARD	New Gift Card-701824338000...	1	25.00	0.00		25.00

Items: 1

Subtotal	Tax	Discount	Total
\$25.00	\$0.00	\$0.00	\$25.00

Past Receipt Sale	Total	Paid	Change

Receipt

Complete the sale and take the proper form of payment. Cash / Credit Card ...

Payment - 25

Dollar Bill Denominations

Type: Cash  
 Amount: 25.00  
 Accept Cancel

Subtotal: \$25.00  
 Total Payment: \$0.00  
 Change:

1 5 10 20 50 100

7 8 9  
 4 5 6  
 1 2 3  
 0 00 .  
 Ca... Cle... Ent...


Cash  
 Credit Card  
 Gift Cert  
 Coupons  
 Next

Complete Sale Cancel Payment

Trans_No	Amount	Description


Finish the sale.

If the scanned gift card is already on file, the screen will show the remaining balance on that card.




Money can be added to the card on this screen. When adding money, select the Add Money button and you will be asked for the dollar amount to add. Complete the sale and receive payment as above.


A second way to sell a gift card is to enter the GCARDXX item number. (Or select it from a speed button if one has been setup)



The system will prompt you to scan the Gift Card number.



Select Exit and the gift card will be activated for the predefined dollar amount.



Take payment as above to complete the sale of the gift card.

4) Use the gift card as payment for merchandise.

After completing a normal sale, select Gift Card from the payment screen.

Sales man View Sales Gift Cards Inventory Credit Cards Override Active Sale No 36252 Management

Item No.	Description	Qty	Price	Disc %
018200610301	BUSCH 30PK	1	22.64	0.00

Subtotal: \$22.64 Tax: \$1.36 Discount: \$0.00 Total: \$24.00

Past Receipt: 36251 Total: \$50.00 Paid: \$50.00 Change: \$0.00

Items: 1

Price Lookup

Complete Cancel Customer

Misc Non-Taxable Misc Taxable Fruit Bags of Candy  
Incense Cup of Ice Slushie Tshirt  
Save Sale Retrieve Sale DISCOUNT  
PROPANE Pop Drawer DISCOUNT Line Discount 10  
Reset AGECHECK

Type: Gift Card Amount: 24.00

Subtotal: \$24.00 Total Payment: \$0.00 Change:

Dollar Bill Denominations: 1, 5, 10, 20, 50, 100

Manual CC Gift Card On Account Previous

Complete Sale Cancel Payment

Trans_No	Amount	Description
Equals:	Equals:	Contains:

The system will ask to scan the gift card.

Gift Card

Scan Gift Card: 7018243380001308

Starting Balance: 40.00

Sale Amount: 24.00

Gift Card Amount to Use: 24.00

New Gift Card Balance: 16.00

Current Sale Balance: 0.00

Use Gift Card

Exit

After scanning, the system will display the sale amount and the remaining balance on the gift card. Select Use Gift Card to complete the sale.

The receipt will show the remaining balance on the gift card.

1 / 1 Pittsburgh Rd  
Butler PA 16001  
724-283-2337

**Sale**


8/21/2024 1:03 PM 36252

Qty	Item	Price
1.0	BUSCH 30PK 018200610301	\$22.64
	Subtotal:	\$22.64
	Sales Tax:	\$1.36
	Total Sale	\$24.00
	Gift Card	-\$24.00
	7018243380001308	
	Bal: \$16.00	


All Sales Final  
No Returns



To see additional information regarding an active gift card, select the Gift Card button at the top of the Point of Sale screen.



Scan the gift card number.



Select Usage Detail to see any sales that used this gift card number as a payment type.  
Clicking on any of the sales listed, will show the receipt from that sale.

Sale No	Trans No	Date	Amount
Equals: ▾	Equals: ▾	Equals: ▾	Equals: ▾
▶ 36252	544774	8/21/2024 1:06:42 PM	24.00

DRIVE-THRU BEVERAGES  
171 Pittsburgh Rd  
Butler PA 16001  
724-283-2337

**Sale**

8/21/2024 1:03 PM 36252

Qty	Item	Price
1.0	BUSCH 30PK 018200610301	\$22.64
	Subtotal:	\$22.64
	Sales Tax:	\$1.36
	Total Sale	\$24.00
	Gift Card	-\$24.00
	7018243380001308	
	Bal: \$16.00	

Print

Exit